Geospatial Scripting Pipeline Programming Basics

This Technical Guide introduces programming basics for setting up and executing an image-processing pipeline in a geospatial script. The illustration diagrams an example: a script to resample an image in a Project File to match a reference image with the output directed to a Project File. (Code excerpts and comments for this script, PipelineResampleToMatch.sml, are on the reverse.) The pipeline in this script includes two sources (input and reference images), one filter (resampling), and one target (see the Technical Guide entitled *Geospatial Scripting: Pipeline Image Processing* for definitions). The example also demonstrates that, although the pipeline architecture is designed to encapsulate image data, properties, and operations, a script can obtain properties from pipeline stages to check for errors and compute values to be used later in the pipeline.

Pipeline stages in the TNTgis geospatial scripting language (SML) are *classes* in the IMAGE_PIPELINE group. The pipeline classes used in this sample script are located there, namely:

- IMAGE_PIPELINE_SOURCE_RVC: an image source created from a raster object in a MicroImages Project File
- IMAGE_PIPELINE_FILTER_RESAMPLE: filter to resample and reproject an image
- IMAGE_PIPELINE_TARGET_RVC: pipeline target that creates a raster object in a Project File
- IMAGE_PIPELINE_GEOREFERENCE: support class to access georeference properties obtained from a pipeline stage

The complete list (with documentation) of available pipeline classes as well as other SML classes and functions can be found in the Script Reference window opened from the SML Editor.

Constructing Pipeline Stages

Classes in SML have *members* (properties that can be read or in some cases changed by your script) and methods (predefined functions that the script can call to operate on class data). Pipeline classes can also have special methods called constructors for declaring a unique instance of the class and defining its parameters. The constructors for source stages, for example, require that you specify the image to be assigned to that particular source. Source stages can refer either to raster objects in Project Files or to external image files such as GeoTIFF. In this sample script the SOURCE_RVC class is used and each source instance is constructed using an instance of class RVC_OBJITEM (in the RVC SYSTEM class group) that refers to the required raster object in a Project File. The script uses a function called DlgGetObject() in the Popup Dialog function group to provide a dialog allowing the user to choose the required raster and populate an instance of RVC OBJITEM.

Constructors for filter stages require that you specify at least one input stage and may require additional parameters. The FILTER_RESAMPLE constructor used here, for example, requires a parameter specifying the resampling method to use. Filter stages can also have different versions of their constructors with different required parameters. There are several versions of the FILTER_RESAMPLE constructor; the one used here specifies a reference image to match in coordinate reference system and cell size, whereas another version omits the reference image and requires an output coordinate reference system and cell size instead.


Constructors for a target stage require that you specify the input filter and identify the output image. For a TARGET_RVC, you pass the constructor an RVC_OBJITEM corresponding to the new output raster object. (Sources and targets for external image types, such as TIFF, are constructed using a FILEPATH class instance, as illustrated in sample scripts PipelineContrastCompositeToTIFF.sml and PipelineNDVIfromTIFF.sml.) Once it is constructed, you can set a compression option for a TARGET_RVC instance using the SetCompression() class method.

Initializing Pipeline Stages

Each pipeline stage class has an Initialize() method that must be called before the pipeline can use that stage. This method checks that all of the specified input stages are properly defined and returns an error code (a negative number) if any do not. As illustrated by the sample script, for debugging purposes a pipeline script should check this error value and return an error to the console or to a popup message dialog to report any errors. This sample script also demonstrates a higher level of error checking: it gets the georeference definition from both input and reference sources to check that each has a valid (though potentially different) coordinate reference system that can then be properly used in the resampling filter.

Processing the Pipeline

Once all of the pipeline stages are defined and initialized, the script initiates processing by calling the Process() class method on the target stage. This method pulls the images through all of the steps of the pipeline and creates the final result image in the designated location.



Annotated diagram of pipeline to resample an image to match a reference image (see PipelineResampleToMatch.sml on next page).

Many sample scripts have been prepared to illustrate how you might use the features of the TNTgis scripting language for scripts and queries. These scripts can be downloaded from www.microimages.com/sml/index.htm.

Pipeline S	cript to Resample/Reproje (PipelineResan	ect Image to Match a Re npleToMatch.sml)	ference Image	
numeric err; error code returned		if (crsRef.IsDefined() == 0 or crsRef.IsLocal()) { PopupMessage("Reference coordinate reference system is undefined or local;		
<pre>proc ReportError(numeric linenum, numeric err) { printf("FAILED -line: %d, error: %d\n", linenum, err); PopupError(err); } define error checking procedure </pre>		exiting script."); Exit(); } else		
clear(); set context so script does not exit on error,		printf("Reference coordinate reference system: %s\n", crsRef.Name);		
_context.AbortOnError = 0; allowing manual handling of errors.		class RVC_OBJITEM rastOutObjI	tem; CHOOSE OUTPUT RASTER	
CHOOSE INPUT IMAGE to be resampled		DlgGetObject("Choose raster for re "NewOnly");	esampled output", "Raster", rastOutObjItem,	
class RVC_OBJITEM riObjItem; objItem for input raster				
DlgGetObject("Select raster to resample:", "Raster", riObjItem, "ExistingOnly");		get line and column cell sizes	s from input and reference images	
PIPELINE SOURCE for input image		class POINT2D scaleIn, scaleRef;	column and line cell sizes of input and reference as x and y values of POINT2D;	
<pre>class IMAGE_PIPELINE_SOURCE_RVC source_In(riObjItem); err = source_In.Initialize(); if (err < 0)</pre>		class POINT2D locIn, locRef;	column and line locations for which to obtain cell size	
ReportError(_context.CurrentLineNum, err); else print("Pipeline source initialized.");		locIn.x = source_In.GetTotalColun locIn.y = source_In.GetTotalRows	nns() / 2; location at center	
printf("Source image has %d lines and %d columns.\n", source_In.GetTotalRows(), source_In.GetTotalColumns());		locRef.x = source_Ref.GetTotalCo locRef.y = source_Ref.GetTotalRo	lumns() / 2; location at center	
check that input image source has valid coordinate reference system		sourceGeoref.ComputeScale(locIn.		
<pre>class IMAGE_PIPELINE_GEOREFERENCE sourceGeoref; sourceGeoref = source_In.GetGeoreference();</pre>		refGeoref.ComputeScale(locRef, scaleRef, 1); reference image in meters		
get coordinate reference system from the source georeference		pixel scale can be negative, so get absolute values		
class SR_COORDREFSYS crs;		<pre>scaleIn.x = abs(scaleIn.x); scaleIn.y = abs(scaleIn.y); scaleRef.x = abs(scaleRef.x); scaleRef.y = abs(scaleRef.y);</pre>		
<pre>crs = sourceGeoref.GetCRS(); if (crs.IsDefined() == 0 or crs.IsLocal()) { PopupMessage("Source coordinate reference system is undefined or local;</pre>		<pre>printf("Input image cell sizes: line = %.2f m, col = %.2f m\n", scaleIn.y, scaleIn.x); printf("Reference image cell sizes: line = %.2f m, col = %.2f m\n", scaleRef.y, scaleRef.x);</pre>		
exiting script."); Exit();		SET APPROPRIATE RESAMPLING METHOD based on relative cell size of input and reference (output) images		
else printf("Coordinate reference system: %s\n", crs.Name);		numeric inCellArea, outCellArea;		
CHOOSE REFERENCE RASTER TO RESAMPLE TO		inCellArea = scaleIn.x * scaleIn.y;	·	
class RVC_OBJITEM refObjItem; DlgGetObject("Select reference raster:", "Raster", refObjItem, "ExistingOnly");		string rsmpMethod\$; if (outCellArea > 2 * inCellArea) then rsmpMethod\$ = "Average"; else rsmpMethod\$ = "CubicConvolution"; printf("Resampling method: %s\n", rsmpMethod\$);		
SET PIPELINE SOURCE FOR F	REFERENCE IMAGE	F6	,	
<pre>class IMAGE_PIPELINE_SOURCE_RVC source_Ref(refObjItem); err = source_Ref.Initialize(); if (err < 0)</pre>		PIPELINE FILTER to resample source image class IMAGE_PIPELINE_FILTER_RESAMPLE filter_rsmp(source_In,		
ReportError(_context.CurrentLineNum, err);		<pre>source_Ref, rsmpMethod\$); err = filter_rsmp.Initialize();</pre>		
else print("Reference source initialized.");		<pre>if (err < 0) ReportError(_context.CurrentLineNum, err); else print("Resample filter initialized.");</pre>		
<pre>printf("Reference image has %d lines and %d columns.\n", source_Ref.GetTotalRows(), source_Ref.GetTotalColumns());</pre>		PIPELINE TARGET: set up the target for the pipeline		
check that reference image has valid coordinate reference system		class IMAGE_PIPELINE_TARGE target_rvc.SetCompression("DPCM	class IMAGE_PIPELINE_TARGET_RVC target_rvc(filter_rsmp, rastOutObjItem);	
class IMAGE_PIPELINE_GEOREFERENCE refGeoref; refGeoref = source_Ref.GetGeoreference();		err = target_rvc.Initialize(); if (err < 0) ReportError(_context.CurrentLineNum, err); else print("Pipeline target initialized.");		
get coordinate reference system from the source georeference		print("Processing");		
class SR_COORDREFSYS crsRef; crsRef = refGeoref.GetCRS();	reference raster's coordinate reference system		ITE pipeline process	