## Select TrueType Interface Fonts

■TNTmips 6.5 Serial# 0067			The font and language support in TNT permits the complete	
显示 编辑 处理	LE 支持 工具栏 常规 帮助	transla	ation of the TNT i	interface
空间数据		to any		wona.
MPEG电影	■TNTmips 6.5 Serial# 0067			
又口 ト	แสดงภาม แก้ไข ประมวลผล สนับ	สนุน แถบเต	ครื่องมือ กำหนดเอง	วธีใช้
参考手册	ข้อมุลเชิงพื้นที่		[	
退出	ภาพยนตร์เคลื่อนไหว		TrueType fort	support nal
A growing list of	แนะนำการใช้เบื้องต้น	٨	clients use for	nts from
anguage kits is available on	การใช้โปรแกรม TNTmips		many sources	i.
microimages.com.	จบการทำงาน			

**Complete Font Support** Virtually everything in the TNT products can be used in all the languages supported. All of the TrueType (scalable) and BDF (fixed) fonts on your computer appear on TNT's Interface Font List Selection dialog (Support/Setup/Fonts). This font support is built in to the MicroImages X Server which uses the X11R6 level on all computer types. TNT uses its own font server to manage TrueType fonts on Windows, Mac and UNIX platforms.

All the pieces are in place for full internationalization. All fonts and languages are supported for

- map legends and annotations
- dialog boxes and messages
- automatic feature labels
- documentation and helpdatabase records
- menu and interface elements

**Encoding Issues** The TNT products use 2-byte Unicode (ISO 10646-1) fonts for TrueType. Note: you may encounter "8859" TrueType fonts for non-Asian alphabets such as Cyrillic (8859-5), Arabic (8859-6), Greek (8859-7), and Hebrew (8859-8). However, 8859 TrueType fonts are 1-byte, non-Unicode fonts and do not work with this version of the TNT products.

Always use Unicode TrueType fonts. The Unicode encoding has code points for all characters, glyphs, and symbols for all written languages. Of course, most Unicode fonts include only selected portions of the huge Unicode character set since they are usually prepared for use in a specific language.

TrueType fonts support a variety of interface	<sup>™</sup> TNTnips 6.5 Serial# 0067	
styles and languages.	Display Edit Process Support Toolbars (uston Help	
TNTmip: Display	y Edit Process Support Toolbars Custom Help	l i
😑 แส่ดงภาพ แก้ไข	ประมวลผล สนับสนุน แถบเครื่องมือ กำหนดเอง วิธีใช้	1
Afbeelden Bewerken	. Verwerken Ondersteuning Werkbalken Keuze Help	
Юђюс№рцжэшж ажфръђ	иматрэшж Юсмрсюђър Юсёы́гцштрэшж Яшъђюумрььћ Юямжфжы	məəl

Follow these steps to use TrueType fonts for the TNT interface elements.

**1. Acquire an Appropriate TrueType Font**. Many fonts are available on the Web either as free downloads or for sale from font vendors. Get the font you need and install it on your system. (For example in Windows 95/98, drag the TTF file to the Windows / Fonts folder.)

2. Download the TNT Language Kit (.PKG) from microimages.com

3. Install the TNT Language Kit. Select Support / Setup / Preferences and click the Install Localization Package button in the General System Preferences dialog. Use the Select File dialog to select the PKG file you downloaded.

4. Select an Installed

Language. Select Support / Setup / Preferences and click the Language ... button. Pick the language you want from the scrolling list in the Language dialog.

## 5. Add Language Fonts.

Select Support / Setup / Fonts and choose a font from the scrolling list in the Interface Font List Selection dialog. The Fonts To Use pane shows the fonts that TNT will use with the currently selected Language. TNT uses the fonts in the order they appear on the Fonts to Use list. Add and Delete fonts for the current Language so that the primary font, size, and style ou want is first. Keep a \_atin-1 font at the bottom of he list as a fallback and any missing interface text will appear in English.

щ яюыќчютрђжыкь бя№ртър