

Database Table Colors

DID YOU KNOW . . . you can assign colors to tabular database views for easier interpretation?



What Database Table Colors Give You

- Ability to change color of the table rows
- Assign alternating colors to table rows
- Show statistics and substatistics rows with a different color
- Interleave two colors for easier record identification


The Color option lets you assign different colors to different rows or groups of rows.

NRD	County	Population
PAPPO-MISSOURI RIVER	Cass	21318
SOUTH PLATTE	Kimball	4108
TWIN PLATTE	Deuel	2237
TWIN PLATTE	Keith	8584
TWIN PLATTE	Perkins	3367

The window background color shows through the selected row color when the Transparent button is toggled on.




The default Color option uses the background window color for all rows.




This toggle button allows you to show statistics and substatistics rows with different colors.

Clicking on any Color button opens the Color Editor window, which lets you change the selected color.

NRD	County	Population
UPPER NIOBRARA WHITE	Daves	9021
UPPER NIOBRARA WHITE	Box Butte	13130
UPPER NIOBRARA WHITE	Sheridan	6750
UPPER NIOBRARA WHITE	Cherry	6307
UPPER NIOBRARA WHITE	Grant	769
Σ	UPPER NIOBRARA WHITE	37526
UPPER REPUBLICAN	Chase	4381
UPPER REPUBLICAN	Dundy	2582
UPPER REPUBLICAN	Hayes	1222
M	UPPER REPUBLICAN	8185
		1578385



NRD	County	Population
PAPPO-MISSOURI RIVER	Cass	21318
SOUTH PLATTE	Kimball	4108
TWIN PLATTE	Deuel	2237
TWIN PLATTE	Keith	8584
TWIN PLATTE	Perkins	3367
UPPER BIG BLUE	York	14428



The Frequency field is active when the Color option is set to *Interleave by row*. The number you enter in this field is the number of rows that will be drawn in Color 1 before changing to Color 2.

How to Assign Database Table Colors

- Click on database table checkbox to open the database table.
- Select Table/Colors from the menu; or select Table/Preferences and click on the Color button.
- Open the Color Interleave option menu and select the desired interleave option.
- Click on color buttons to open the Color Editor and assign the desired colors.
- Make sure the Transparent toggle is off when colors are assigned.

WANT TO KNOW MORE?



See the tutorial booklet entitled:
Managing Geoattributes

