
Elements in View Controlled by Scale

DID YOU KNOW ... you can control which elements in a layer are visible as you zoom in and out?

What Controlling Visible Elements by Scale Gives You


- Eliminate clutter when zoomed out
- Increase detail as you zoom in
- Decrease drawing time at full view



elements drawn

zooming in again

adds railroads





┷┿┿┿┿┿	🕂 🔰 🌈 are usi	ng the Cla	ass Codes
		otion field	
	determ	ine line v	risibility.
╞╪╡╪╪╴	\ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \		
ome	zooming in once adds Tr	nis road ty	/pe is visible
ted b	y water features or	ily when y	ou zoom in
Political boundaries and primary beyond 1:100000.			
	GER / TGRLINEDB / ElementVisRange		
Tab			LOX Help
			Help
	le Edit Record Field	MinScale	Help MaxScale
Tab 1↓↓	le Edit Record Field	MinScale	Help
	le Edit Record Field	minScale	Help MaxScale
	le Edit Record Field Description Neighborhood, city and unimproved roads Nonvisible Political Boundary Primary, interstate and 1td access road		Help MacScale 100000 0 0
	le Edit Record Field Description Neighborhood, city and uninproved roads Nonvisible Political Boundary Primary, interstate and Itd access road Railroad main track		Help HakScale 100000 (Å 0 0 200000
	le Edit Record Field Description Neighborhood, city and unimproved roads Nonvisible Political Boundary Primary, interstate and 1td access road		Help Help 100000 [4 0 200000 350000
	le Edit Record Field Description Neighborhood, city and uninproved roads Nonvisible Political Boundary Primary, interstate and Itd access road Railroad main track		Help HakScale 100000 (Å 0 0 200000

Scale Selection Attribute

CFCC

Class_Codes.Description

Description

Feature_Type

Select the attribute with values that will determine the visible map scale for elements. In this case, we

Table

nternal

lass_Codes

Geo_Area_Cod

Basic_Data

Help

Field

You can enter the MinScale and MaxScale values immediately after designating the scale selection attribute. You can also enter or change these values after the object is displayed, but you must turn on the Show Internal Tables toggle for the table to be shown.

How to Set Up Control for Visible Elements By Scale

- Select a vector, CAD, or TIN object for display, set the desired element selection to By Map Scale (Object Layer Controls), and click [Specify].
- Select or create a scale-selection table, and choose the pertinent attribute.
- Enter the minimum and/or maximum scale at which elements with selected attributes will be visible (leave blank for elements to show at all scales).
- Close the table and click [OK] in the Object Layer Controls window.

WANT TO KNOW MORE?



Search the information available on Microlmages' Web Site

