Refresh Tabular Views of Linked Tables

Database tables you use with spatial data in the TNT products can actually reside in an external database (Oracle, SQL Server, MySQL, MS Access, or others) which provides Open Database Connectivity (ODBC). Each time you open a linked table in a TNT product, the current external data (including any updates made since you last viewed

■Group 1 - Group Controls Group Layer Options • <u>k</u> <u>ii 😘 📜 🖘 📎</u> ParcelInfo Link to ParcelInfo table in MS Access Parcels Parcel IDs ■Parcels3 / PolygonDatabase / ParcelInfo Table Edit Record Field ************ OwnerFirstName ParcelID OwnerLastN Dickens Charles SC111874 Residential SC145982 Residential ■Prefere SC182395 Asimov Tsaac Residential SC203845 Chandler Raymond Connercial Grid Lines SC218977 LeGuin Ursula Farm ■ Horizontal SC223403 Residential John Fowles ■ Vertical 52 of 52 records shown **□** 3D F Realtime Scrolling Use the Refresh button to manually ☐ Hide Unattached Records update the tabular view of a linked F Auto Scroll to First Selected Record table. Vertical Scrollbar Tip: Sorted Field ▼ Turn on the Refresh toggle on the Colors Preferences window (Table / Refresh every 10 Seconds Preferences) to enable automatic OK Cancel Help refresh of a linked table.

it) are presented in your view of the table and used in any processes. However, the external database software may allow the data to be accessed and updated by others while you are viewing it. Unfortunately, ODBC does not provide a means to automatically notify database clients (in this case your TNT process) that the source table has been changed.

There are now several ways in which you can have an open tabular view of a linked table check the external database and update or "refresh" your view of the data. You can do this manually using the Refresh icon button on the tabular view window. If you would like the table to automatically refresh, you can turn on the Refresh toggle button on the Preferences dialog window for that table (accessed using the Table / Preferences menu option). Associated with this toggle is a numeric field in which you set the time interval in seconds for the refresh cycle. Note that setting a very small refresh interval (less than a few seconds) for a large table may slow your viewing operations.


Refresh via SML

A linked table can also be updated by a Visual Basic / ActiveX component program run from an SML tool script, as described in the color plate entitled *Communicate with Visual Basic Programs*

using SML (www.microimages.com/documentation/68visbasic.pdf). The tool script enables selection of elements from the View window for updating via a Visual Basic dialog. A new SML function is now available for use when the Visual Basic program has notified SML that the external database table has changed. The TableTriggerRecordChangedCallback(table,

recordNum) function alerts the RVC file managment system that the table has changed. This alert then triggers a redraw in the

View of any individual elements to which the updated records are attached. Thus if the table update results in a change in style for the selected element, that style change is applied during the redraw. See the color plate entitled *Visual Basic Callbacks to SML* for examples of the use of this function.



■Parcels / Group_2 - Group View 1

Tool LegendView GPS Options

Helo